




















































N-8000 Programming software (French version installation)

In order to use the N-8000 software in French you must change your language settings and import the appropriate language file. Please also note that this is only for the programming software and it will not change the default text on the master stations from English.


- 1) Locate the default Program Files folder on your computer. This is typically located here:
C:\Program Files (x86)\TOA\N-8000 You will notice that there is already a LNG file in this directory.

Name	Date modified	Type	Size
 MaintenanceSoft	11/14/2014 11:41 ...	File folder	
 RecordingSoft	7/12/2013 9:27 AM	File folder	
 ConfigurationSoft	12/16/2014 7:35 AM	Application	1,506 KB
 configurationsoft_ja	9/29/2014 9:44 AM	LNG File	22 KB
 Dictionary.DLL	12/16/2014 7:35 AM	Application extens...	10 KB
 EmergMsg	8/11/2014 9:53 AM	Application	1,123 KB
 IPConfig_N8000.DLL	12/16/2014 7:35 AM	Application extens...	27 KB
 IPConfigTool.DLL	12/16/2014 7:35 AM	Application extens...	68 KB
 N85XX	6/6/2014 9:20 PM	VLC media file (.bi...	2,046 KB
 N8000	8/25/2008 10:59 AM	Application	2,346 KB
 N8000Config	7/7/2014 5:16 PM	SQL Server Databa...	2,240 KB
 N8000Config_log	7/7/2014 5:16 PM	SQL Server Databa...	832 KB
 N8000EX	10/28/2014 2:00 PM	VLC media file (.bi...	1,472 KB
 N8000MI	10/28/2014 2:32 PM	VLC media file (.bi...	1,462 KB
 N8000msg_ja.dll	10/25/2013 9:26 AM	Application extens...	875 KB
 N8000UNIT	10/28/2014 9:23 AM	VLC media file (.bi...	1,664 KB
 N8010EX	10/16/2014 6:16 PM	VLC media file (.bi...	1,472 KB
 N8600	10/17/2014 9:14 AM	VLC media file (.bi...	2,501 KB
 N8616MS	10/28/2014 2:44 PM	VLC media file (.bi...	1,664 KB
 PresentationFramework.Aero.dll	8/3/2013 1:41 PM	Application extens...	192 KB
 SX200IP	11/5/2014 9:22 AM	VLC media file (.bi...	2,308 KB
 TOA.CommonLib.Net.DLL	12/16/2014 7:35 AM	Application extens...	41 KB
 toa	5/26/2014 4:40 PM	Icon	23 KB
 WPFHelper.DLL	12/16/2014 7:35 AM	Application extens...	68 KB
 WPFToolkit.DLL	5/26/2014 4:40 PM	Application extens...	214 KB

2) Take the provided language file configurationsoft_fr and import it into this folder.

Name	Date modified	Type	Size
 MaintenanceSoft	11/14/2014 11:41 ...	File folder	
 RecordingSoft	7/12/2013 9:27 AM	File folder	
 ConfigurationSoft	12/16/2014 7:35 AM	Application	1,506 KB
 configurationsoft_fr	7/21/2016 9:20 AM	LNG File	19 KB
 configurationsoft_ja	9/29/2014 9:44 AM	LNG File	22 KB
 Dictionary.DLL	12/16/2014 7:35 AM	Application extens...	10 KB
 EmergMsg	8/11/2014 9:53 AM	Application	1,123 KB
 IPConfig_N8000.DLL	12/16/2014 7:35 AM	Application extens...	27 KB
 IPConfigTool.DLL	12/16/2014 7:35 AM	Application extens...	68 KB
 N85XX	6/6/2014 9:20 PM	VLC media file (.bi...	2,046 KB
 N8000	8/25/2008 10:59 AM	Application	2,346 KB
 N8000Config	7/7/2014 5:16 PM	SQL Server Databa...	2,240 KB
 N8000Config_log	7/7/2014 5:16 PM	SQL Server Databa...	832 KB
 N8000EX	10/28/2014 2:00 PM	VLC media file (.bi...	1,472 KB
 N8000MI	10/28/2014 2:32 PM	VLC media file (.bi...	1,462 KB
 N8000msg_ja.dll	10/25/2013 9:26 AM	Application extens...	875 KB
 N8000UNIT	10/28/2014 9:23 AM	VLC media file (.bi...	1,664 KB
 N8010EX	10/16/2014 6:16 PM	VLC media file (.bi...	1,472 KB
 N8600	10/17/2014 9:14 AM	VLC media file (.bi...	2,501 KB
 N8616MS	10/28/2014 2:44 PM	VLC media file (.bi...	1,664 KB
 PresentationFramework.Aero.dll	8/3/2013 1:41 PM	Application extens...	192 KB
 SX200IP	11/5/2014 9:22 AM	VLC media file (.bi...	2,308 KB
 TOA.CommonLib.Net.DLL	12/16/2014 7:35 AM	Application extens...	41 KB
 toa	5/26/2014 4:40 PM	Icon	23 KB
 WPFHelper.DLL	12/16/2014 7:35 AM	Application extens...	68 KB
 WPFToolkit.DLL	5/26/2014 4:40 PM	Application extens...	214 KB

- 3) After you have copied this LNG file into your directory you now need to change your default language settings for French. Go to Control Panel, Language / Region Settings and change this to French (Canada) Click Apply to confirm your changes.



- 4) Now, when you open your N-8000 programming software the langue, settings, etc. will all be in French.

